


Windows Mobile POP 3 E-mail Setup

1. Go to your Messaging Application and select **Setup E-mail**.



2. Next the E-mail Setup screen will appear. **Uncheck** the box next to "Try to get e-mail settings automatically from the internet". Click **Next**.



3. Enter your BWIG E-mail address and Password. Click **Next**.



Messaging 3G 2:31

E-mail Setup ?

E-mail address:


@

Password:

Save password

Cancel  Next

4. You will now need to select your email provider. Select the **Internet e-mail** option from the drop down list. Click **Next**.



Messaging 3G 2:32

E-mail Setup ?

Your e-mail provider:

Internet e-mail ▼

Your Internet service provider (ISP) or webmail provider supports POP or IMAP e-mail. If unsure, contact your provider.

Previous  Next

5. Enter both **your name** and the **display name** you wish to use. The account display name is only used to identify your account on the mobile device you are using. Click **Next**.

Messaging 3G 2:32

E-mail Setup

Your name:
Bob Smith
(Example: Kevin Cook)

Account display name:
wks231.qatest.local
The name for this account on this device.

123 1 2 3 4 5 6 7 8 9 0 - = ◀
Tab q w e r t y u i o p []
CAP a s d f g h j k l ; ' ◀
Shift z x c v b n m , . / ◀
Ctl á ü ` \ ◀ ▶ ◀ ▶

Previous Next

6. This next screen will display your **incoming server settings**. Enter the following information:
- Incoming mail server – mail.bwig.net
 - Account Type – Select POP3 from the drop down list
 - Port – 110
 - Click **Next**

Messaging 3G 2:33

E-mail Setup

Incoming mail server:

If unsure, check with your provider to get POP/IMAP settings.

Account type:
IMAP4

Previous Next

7. Now enter your username and password again. Make sure to enter your full BWIG e-mail address (ex. *jdoe@bwig.net*) for the user name. Click **Next**.

Messaging 3G 2:33

E-mail Setup

User name:

(Examples: kevinc, domain\kevinc,
kevinc@contoso.com, etc.)

Password:

Save password

123 1 2 3 4 5 6 7 8 9 0 - = ◀
Tab q w e r t y u i o p []
CAP a s d f g h j k l ; '
Shift z x c v b n m , . / ↵
Ctl áü ` \ | ↓ ↑ ← →

Previous Next

8. You will now be prompted to enter your **outgoing mail server** settings. Enter the following information:
- Outgoing Mail Server – mail.bwig.net
 - Check the box next to “*Outgoing server requires authentication*”
 - Check the box next to “*Use the same user name and password for sending e-mail*”
 - Click **Next**

Messaging 3G 2:33

E-mail Setup

Outgoing (SMTP) mail server:

Outgoing server requires authentication

Use the same user name and password
for sending e-mail

[Advanced Server Settings](#)

Previous Next

9. The final setup screen will appear now. Select how often you wish to have your mobile device check for new messages from the drop down box. After this, click **Finish**. You will now have successfully setup e-mail on your Windows Mobile Device.

